



Tierra del Sol Industrial Park - 2329 Lava Lane
PO Box 642, Alamosa, CO 81101
Phone: 719-589-1024
Email: juliez@sangrelabs.com
www.sdclaboratory.com

Chain of Custody

PAYMENT IS DUE AT TIME OF SAMPLE DROP-OFF. NO EXCEPTIONS.

PLEASE FILL OUT INFORMATION BELOW	
Client Name:	_____
Phone Number:	_____
Address of Sample:	_____
Date Collected:	_____
Time Collected:	_____
Collected By:	_____
Email:	_____

Analysis(es) Requested Private Well Package (includes bacteria test) \$195

Loan Package (includes bacteria test) \$100

Bacteria Only \$35

Other _____

ALL PRICES SUBJECT TO CHANGE

Signature (Relinquished by): _____

Date/Time: _____

FOR LAB USE ONLY

Received by: _____

Date/Time: _____ Lab Sample Number: _____

Thank you! We appreciate you and are always here to help!



Tierra del Sol Industrial Park - 2329 Lava Lane
PO Box 642, Alamosa, CO 81101
Phone: 719-589-1024
Email: juliez@sangrelabs.com
www.sdclaboratory.com

PROPER SAMPLE COLLECTION IS IMPORTANT - PLEASE USE INSTRUCTIONS BELOW TO ENSURE BEST RESULTS

FOR PRIVATE WELL & LOAN PACKAGES (Three bottle numbered set)

- 1. PREPARATION:** Be sure to wash your hands with soap and warm water prior to collecting sample. Remove any filtration equipment/screens and thoroughly disinfect faucet with rubbing alcohol or bleach. Use *ONE* faucet to collect water for *ALL THREE* bottles.
- 2. COLLECT BOTTLE #1:** For Bottle #1, collect in the morning before any water has run.
- 3. COLLECT BOTTLES #2 AND #3:** After collecting Bottle #1, run the water for 2-3 minutes then collect Bottle #2 and Bottle #3. Fill **Bottle #3** to '**Fill Line**' indicated on the bottle. Samples under the 'Fill Line' are subject to rejection. Take care NOT to touch the bottle opening or inside the bottle. Do not rinse bottle before collection. Samples need to be kept cool and delivered to the lab within 24 hours.
- 4. SUPPLEMENTAL PAPERWORK:** Complete this form and clearly write your name on your sample bottle.

FOR BACTERIA SAMPLES (Flip top bottle with pill/powder inside)

- 1. PREPARATION:** Be sure to wash your hands with soap and warm water prior to collecting sample. Remove any filtration equipment/screens and thoroughly disinfect faucet with rubbing alcohol or bleach.
- 2. COLLECTION:** Let water run for 2-3 minutes and then collect sample. Fill bottle to '**Fill Line**' indicated on the bottle. Samples under the 'Fill Line' are subject to rejection. Take care NOT to touch the bottle opening or inside the bottle. Do not rinse bottle before collection. Samples need to be kept cool and delivered to the lab within 24 hours.
- 3. SUPPLEMENTAL PAPERWORK:** Complete this form and clearly write your name on your sample bottle.

Payment is due at time of sample drop-off

FOR ALL OTHER SAMPLES (If in doubt, call us)

- 1. COLLECT SAMPLE:** Collect sample from desired location. Samples need to be kept cool and delivered to the lab within 24 hours.
- 2. SUPPLEMENTAL PAPERWORK:** Complete this form and clearly write your name on your sample bottle.

Thank you! We appreciate you and are always here to help!